


Settings for the JTDX-Helper V 1.7.2

Following settings are required in the Main Window of JTDX:

- Auto TX: Green, will be set automatically
- Auto Seq: Green, AutoSeq-1, 2 or 3. **Caution! AutoSeq 4+ is not supported !**
- Lockd TX/RF: In S&P yellow, in RUN green, will be set automatically
- Monitor: Green, will be set automatically
- Enable Tx: Will be set by JTDX-Helper
- Menu: Checked (**Important**)
- Spt: Not checked
- Horizontal splitting: This is a very important setting, especially if Band-hopping is used. Splitting shifts all buttons in the right window. As the Frequency selection button is tiny, this setting should be done with care. The optimal setting is, if you could read a full DXCC entity e.g. *VP8M.



Settings in „Settings – General“

- My Call / My Grid: According your own station
- IARU Region: All *
- Use current call-sign: Checked *
- Use current grid: Not checked *
- Blank line between decoding periods: Checked (recommended) *
- TX messages to Rx frequency window: Checked
- Show DXCC, grid und Show prefix or name: Both checked
- Behaviour: All **not** checked *
- TX watchdog timer: 6 minutes *
- Tune timer: 30 sec *
- CW ID after 73: Not checked *
- Period CW ID interval: 0 *

Settings marked by “*” might be not important, but tests were made with the written settings above.

Required in “Settings – Radio und Audio“

According your TCVR and Interface

Required in “Settings – Sequencing“

All setting must be off. The JTDX-Helper has its own QSO supervising.

Required in “Settings – TX Macros“

Already entered TX-Macros will be not used by the JTDX-Helper.

Required in “Settings – Reporting“ (Important!)

- Prompt me to log QSO: **Not** checked
- Enable automatic logging of QSO: **Checked**

All other settings in „Reporting“ are not relevant for the FTDX-Helper

Required in "Settings – Frequencies" (important for Band-Hopping)

All not used FT4 and FT8 frequencies should be deleted, so that only the required ones are listed in the frequency selection pulldown menu. Note that the JTDX-Helper cannot pull the vertical bar to select a band.

Required in "Settings – Notification"

Important! The default colours must not be changed.

- New one and worked B4 status notifications: According your needs, but no invers colours. JTDX-Helper calls In S/P mode only stations matching to the selected entries. The stations with the highest priority will be called first. The highest priority can be selected is „CQZ“.
- Red / my call in message Checked
- Highlight worked ones Checked, with strike or underline

Required in „Settings - Filters“.

For correct working of Automatic Frequency Setting (AFRQ), all filter must be switched off, or „Bypass“ shall be activated.

Setting in „Waterfall (Wide-Graph)“.

Following settings are only requested if "Auto-Frq" is used.

- Horizontal width: from 500 Hz up to 2850 Hz must be visible.
- Bins/Pixel: 3
- Start: 500 Hz
- All other settings are not critical

73'DX,

Geza DG5LP

Feedback to: dg5lp@darcd.de
